



# Zip data

Written By: StJohn Vuetilovoni




## INTRODUCTION

Use this guide to back up all data currently stored in the database to a zipped file.


**Note:** It assumes you have already [installed the monitor's configuration software](#), [downloaded the cable driver](#) and [connected your monitor to a PC](#).

## Step 1 — Zip data




- [Launch the Aeroqual S500 software](#) and select **File > Database Management > Zip Database** from the menu bar.
- Select a directory, enter a file name and click **Save**.

## Step 2 — Unzip data



- To view archived data, select **File > Database Management > Unzip Database** from the menu bar.
- Select the required .zip file and click **OK**.
- To view and analyze data, select **Data > Table > Logged**.

 Don't view archived data on the same PC used for data logging. If you do, logging is stopped and

---

current data in the database is lost  
(unless it's been zipped).

---

For further support, contact [Technical Support](#).